RSA NetWitness Logs

Event Source Log Configuration Guide



Microdasys XML Security Gateway

Last Modified: Monday, May 22, 2017

Event Source Product Information:

Vendor: Microdasys

Event Source: XML Security Gateway

Versions: 1.1.0

Additional Downloads: sftpagent.conf.microdasys_xsg

RSA Product Information:

Supported On: NetWitness Suite 10.0 and later **Event Source Log Parser**: microdasys_xsg

Collection Method: File

Event Source Class. Subclass: Security. Application Firewall

To configure Microdasys XML Security Gateway, complete the following tasks:

- I. Configure Microdasys XML Security Gateway
- II. Set Up the SFTP Agent and Configure the NetWitness Log Collector

Configure Microdasys XML Security Gateway

To configure Microdasys XML Security Gateway:

- 1. Log on to Microdasys XML Security Gateway with administrator credentials.
- 2. Click Config > Logging.
- 3. Ensure that **Edit all servers** is selected.
- 4. Ensure that the default log location is selected.

Note: If your default log location is different than C:/Program Files (x86)/Microdasys/XSG/log/, update the path in the sftpagent.conf.microdasys_xsg file to match the path displayed in the XML Security Gateway console.

- 5. Ensure that **Access Log** is selected and that the corresponding **File:** xsg_access.log checkbox is selected.
- 6. Click Apply.

Configure File Collection for RSA NetWitness Suite

To complete the File collection configuration, perform these tasks:

- I. Set up SFTP Agent
- II. Configure the RSA NetWitness Suite Log Collector for File Collection

Set Up the SFTP Agent

To set up the SFTP Agent Collector, download the appropriate PDF from RSA Link:

- To set up the SFTP agent on Windows, see Install and Update SFTP Agent
- To set up the SFTP agent on Linux, see Configure SA SFTP Agent shell script


Configure the Log Collector for File Collection

Perform the following steps to configure the Log Collector for File collection.

To configure the Log Collector for file collection:

- 1. In the NetWitness menu, select Administration > Services.
- 2. In the Services grid, select a Log Collector, and from the Actions menu, choose View > Config > Event Sources.
- 3. Select File/Config from the drop-down menu.
 - The Event Categories panel displays the File event sources that are configured, if any.
- 4. In the Event Categories panel toolbar, click +.


The Available Event Source Types dialog is displayed.




5. Select the correct type from the list, and click **OK**.

Select microdasys xsg from the Available Event Source Types dialog.

The newly added event source type is displayed in the Event Categories panel.



6. Select the new type in the Event Categories panel and click + in the Sources panel toolbar.



The Add Source dialog is displayed.

- 7. Add a File Directory name, modify any other parameters that require changes, and click **OK**.
- 8. Stop and Restart File Collection. After you add a new event source that uses file collection, you must stop and restart the NetWitness File Collection service. This is necessary to add the key to the new event source.

Copyright © 2017 EMC Corporation. All Rights Reserved.

Trademarks

RSA, the RSA Logo and EMC are either registered trademarks or trademarks of EMC Corporation in the United States and/or other countries. All other trademarks used herein are the property of their respective owners.